

# Disinfectants

## Microcide

Glutaraldehyde 150g /L  
Dimethyl cocobenzylammonium chloride 100g /L  
Pine oil 50g /L

For routine disinfection, dilute at a rate of 1:200 and apply 300ml per square meter.

To control major pathogen causing septicaemia, enteritis, respiratory diseases and canine parvovirus, 1:50.

Disinfection of drinking water, 1:3000.

## Microtex

Glutaraldehyde 150g /L  
Dimethyl cocobenzylammonium chloride 100g /L

For routine disinfection, dilute at a rate of 1:200 and apply 300ml per square meter.

To control major pathogen causing septicaemia, enteritis, respiratory diseases and canine parvovirus, 1:50.

Disinfection of drinking water, 1:3000.

## Germicide

Glutaraldehyde 62.5g /L  
Dimethyl cocobenzyl ammonium chloride 50g /L  
Didecyl dimethyl ammonium chloride 37.5g /L  
Octyl decyldimethyl ammonium chloride 37.5g /L

For routine disinfection, dilute at a rate of 1:200 and apply 300ml per square meter.

Foot dips, 1:100

Wheel dips, 1:100

Vehicle & Equipment spray, 1:100

## Viruxéal

Pentapotassium Peroxymonosulfate 50%

For routine disinfection, dilute at a rate of 1:100 and apply 300ml per square meter.

Foot dips, 1:100

Wheel dips, 1:100

Vehicle & Equipment spray, 1:100

Water system, 1:100 - 1:200

Misting/fogging, 1:200



# Disinfectants

## Iodophor

Iodine 30g /L

For cleaning and disinfection of livestock houses and equipment, 1:500 (200ml to 100L).

For disinfection against foot&mouth disease virus: 1:250 (400ml to 100L).

For fogging and spraying houses and equipment: 1:350 (300ml to 100L)

For foot baths and vehicle dips: 1:180 (550ml to 100L)

## Biospray

Iodine 10g /L

For cleaning and disinfection of wounds.

Apply directly on the wound either via spray or pour.

## Mastodip

Iodine 10g /L

Sorbitol + Glycerin 150g /L

**Pre-Milk Dipping:** Before each cow is milked, and using fresh Mastodip, dip each teat full-length

into the teat dip cup. Wipe teats after dipping using single-service towels to avoid contamination of milk.

**Post-Milk Dipping:** Using fresh Mastodip, dip each teat full-length into the teat dip cup. Do not

wipe. Allow to air dry. Do not turn cows out in freezing weather until the product is completely dry.

**Pre-Milk Spraying:** Before each cow is milked, and using fresh Mastodip spray entire teat. Wipe teats after dipping using single-service towels to avoid contamination of milk.

**Post-Milk Spraying:** Using fresh Mastodip spray entire teat immediately after each milking. Do not wipe. Allow to air dry. Do not turn cows out in freezing weather until the product is completely dry.

